

Ring Bearer's Pillow

Embellished with Kreinik Iron-on Threads

Designed by Nancy Billetdeaux



Materials needed:


- 3/8 yards of white satin fabric
- Kreinik 1/8" Ribbon 6010 Pearl
- Kreinik Teflon Press Cloth
- Iron or Clover Mini Iron and ironing surface
- 3/16" White Feather Edge Ribbon, 18 inches
- 1/4" White Sheer Ribbon, 18 inches
- 5/8" White Sheer Ribbon, 18 inches
- 2 silver wedding bands (available at craft stores)
- 3 white ribbon roses (about 5/8" diameter)
- 1 green Tri Leaf with stem (small)
- Poly-fill stuffing
- Needle, white thread, sewing machine, scissors
- 6 to 8 inches of green florist tape
- 62 inches of Dental floss
- disappearing pen
- tape measure

Instructions:

Refer to the photo as a guide. Print out these instructions and the heart pattern.

1. Trace and cut out the heart pattern. Place pattern onto double thickness of white satin fabric and cut out heart. Transfer markings from pattern onto one right side of heart.
2. Turn your iron on to the highest setting, and allow it to heat thoroughly. Iron on pearl ribbon onto right side of heart that is marked, using Teflon Press Cloth.
3. For ruffle: cut two strips of white satin fabric 4 inches by 25 inches. With right sides together, sew short ends together using a 5/8" seam allowance forming a circle.
4. Fold fabric circle wrong sides together. Zig zag along raw edges.
5. Cut two pieces of dental floss, each about 31 inches long. Using a wide zig zag basting stitch, stitch over dental floss leaving enough to hold onto at the beginning and the end, and start a new piece of dental floss at each seam (this makes it easier to gather).
6. Place one seam of ruffle at point on right side of one heart and the other seam at the center top of heart. Adjust gathers around heart and pin in place. Zig zag close to edge. Remove pins.
7. Place right sides of hearts together and stitch around entire heart using a 1/2" seam allowance, and leaving an opening for stuffing. Clip curves. Turn right sides out and stuff. Slipstitch opening closed using white thread.
8. Cut a piece of Iron-on pearl ribbon to 18 inches. Place ribbons together along with the Iron-on ribbon and tack to front of pillow referring to photo for placement.
9. Place leaf stem and three ribbon roses together using florist tape, stretch and pull, covering flower stems and leaf stems joining them together.
10. Tack leaf and roses to ribbon where ribbon was tacked. Place two rings over one side of ribbon and tie in a bow.
11. Handle: cut two pieces of white satin fabric 8 1/2" x 2", with right sides together pin along long sides turning under 3/8" on each short end. Stitch 3/8" on each long side. Turn right sides out and press. Slipstitch short sides of handle to back sides of heart.

© Copyright 2004 Kreinik Mfg. Co., Inc. Consumer Information: 1-800-537-2166 or email us at kreinik@kreinik.com. Call us or visit the shop locator at www.kreinik.com to find a source of Kreinik Iron-On Threads near you.



Place on fold.

HEART
PATTERN
CUT 2
WHITE
SATIN